

## WALL-E Software Walk Through

### Convert any to .ASF video files to .mkv

- Install Handbrake (video file format conversion software)
- Click "Open Source", select .ASF file you want to convert



- Select MKV as destination file format
- Check "Constant Framerate" in the "Video" tab



Python Information (Read this before the rest of the tutorial)

- Use Python version 2.7
- Install the following dependencies:
  - OpenCV for Python
  - o Pillow
    - pip install Pillow
- (info) Dependencies used that come with Python 2.7
  - o NumPy
  - o Tkinter

#### Clone our Git Repository

- In terminal:
  - o git clone https://github.com/vincentwangg/WALL-E

#### Isolate Clip using Timestamp

- Use <u>WALL-E/wall-e/utils general/video clip generator.py</u> to generate clips
  - o in wall-e/ directory

```
o run "PYTHONPATH=. python
  utils_general/video_clip_generator.py
  <left_video_file_name> <right_video_file_name> frame -l
        <start_second> <end_second>
o <start_second> is the time the clip starts in seconds (e.g. 4:30 would be 270)
```

<end second> is the time the clip ends in seconds (e.g. 4:50 would be 290)

#### Run GUI script (runs frame matching, stereo rectification)

- Using WALL-E/wall-e/pipeline1 gui.py
  - Run "python pipeline1 gui.py"
  - o Follow the instructions through the interface
  - Problem: Two videos aren't framed matched and stereo rectified
  - Output: Stereo rectification map and/or stereo rectified and frame matched footage

# Run Pipeline2 (pulse matches, and outputs 3D mapping results to text file) - Karthik

- Make sure you're in the directory ~/WALL-E/wall-e
- run "PYTHONPATH=. python pipeline2.py <left\_video\_file\_name> <right video file name> <baseline distance>"
- baseline should be in mm

#### Install Blender

- <u>Tutorial</u>
- Used to model 3D data

#### Import Pulse Data in to Blender

https://github.com/vincentwangg/WALL-E/wiki/Blender